



## Pump Genius Multiplex V2.30 Application Information

Equipment: CFW-11

Firmware Version: Ve5.31

WLP Software Version: V9.95 or higher

New Application Version: PGMPX\_CFW11\_en\_V2\_30.apl

Old Application Version: PGMPX\_CFW11\_en\_V2\_20.apl

Document Number (Application Manual): 10001912293 / 03

### Functional deviations in the old application version

- 1) There is not.

### Changes in the new application version

- 1) It was implemented the sleep boost function;
- 2) It was implemented the indication of master pump active in the digital input DO2.



**NOTE!**

Appendix 1 shows how to import Pump Genius Multiplex application to WLP.

## Appendix 1 – How to Import Application to WLP

- 1) In the WLP Ladder Programmer, in “Tools” menu, select the “Import Application to WLP” option;
- 2) Search “PGMPX\_CFW11\_en\_V2\_30.apl” archive and press “OK”;
- 3) The Pump Genius Multiplex application will be imported to WLP;
- 4) To select the application, in “Tools” menu, “Application” option, “CFW11”, “Create”, “Pump Genius”, select “Multiplex” option.